

FPS/Network Display Box ("F" key in-game)

Authored by: **John Bodin** [jbodin@sbcglobal.net]

Saved From: <http://faq.iracing.com/article.php?id=148>

Pressing "F" on your keyboard will enable the FPS/Network Display box, which shows your graphics performance in Frames Per Second, along with your Network connectivity detail display. The FPS/Network Display box appears in the upper right-hand corner of the screen when you're in-car and on the track:



The FPS/Network Display box shows you four values:


FPS (graphical frame rate in Frames Per Second, or FPS)

L(Latency, or data transmission delay between your system and the iRacing server)

Q (Quality of the connection to the iRacing server)

S (Service, showing the state of Synchronization between your computer and iRacing)

P (Page fault meter, indicates if you are experiencing system page faults related to memory settings)



The "FPS" indication at the top of the display is a numerical value that represents your frame rate in Frames Per Second (FPS), which is a reflection of your graphical performance.

The "L" portion is a bargraph that represents your latency of your connection, or the time delay for data transmitted between your PC and the iRacing servers. This bar can vary in length and in color -- a shorter bar length or a green bar indicates a low latency or delay, and if this bar turns red that indicates that your latency is reaching an unacceptable acceptable level. When you see a red bar here, this is an indication that the latency has dropped to an acceptable level, which may result in a disconnection from the iRacing server.

The "Q" portion is a bargraph that represents your connection quality, and this bar can display varying colors -- a green bar is good, yellow or orange means less than ideal connection quality, and it will turn red if your quality is dropping below an acceptable level. When you see a red bar here, this is an indication that your connection may drop and you may be disconnected from the iRacing server.

The "S" portion shows the service/synchronization state, or the "skew" of your connection to the iRacing servers. As with the "Q" bar, a green bar is good, yellow or orange means less than ideal synchronization with the iRacing service, and it will turn red if your synchronization is dropping below an acceptable level. When you see a red bar here, this is an indication that your connection may drop and you may be disconnected from the iRacing server.

The "P" portion is your page fault meter, which indicates if you are experiencing page faults because your system is using your disk drive to make up for lack of available physical RAM. If you are seeing a solid yellow or red bar in the "P" meter, you may be experiencing reduced video performance -- to eliminate the yellow or red bars, the easiest solution is to lower the GPU Video Memory slider (move it to the left) in the advanced graphics options to make the simulation use less RAM. If this doesn't work you may benefit by adding RAM to your PC. Other processes and services running on your PC also use RAM, so it can help to reboot your PC and close down as many application as possible before running the simulation - to free up as much physical memory as possible.

OPTIONS



DISPLAY

- Window Resolution: 1920x1024 Full Screen Monitor width including bezel: in
- Interface Zoom: 100% Visible width excluding bezel: in
- Number of screens: 1 Viewing distance: in
- Render each screen separately Angle between center and side screens: °
- Field of view when driving (45° to 160°): °

PERFORMANCE

Max Quality  Max Frame Rate

CUSTOM

- | | | |
|---|---|--|
| <input checked="" type="checkbox"/> Cars: Medium Detail | <input checked="" type="checkbox"/> Shadow maps on track/cars | <input checked="" type="checkbox"/> Hide Steering Wheel |
| <input checked="" type="checkbox"/> Pit Objects: Low Detail | <input checked="" type="checkbox"/> Trackside objects | <input checked="" type="checkbox"/> Virtual Mirror: 35° |
| <input checked="" type="checkbox"/> Event: Low Detail | <input checked="" type="checkbox"/> Prefer shadow maps | <input type="checkbox"/> Cockpit Mirrors |
| <input checked="" type="checkbox"/> Grandstands: High Detail | <input type="checkbox"/> Shadow volumes | <input type="checkbox"/> Higher Detail in Mirrors |
| <input checked="" type="checkbox"/> Crowds: Low Detail | <input type="checkbox"/> 2-Pass | <input type="checkbox"/> Headlights on track in mirrors |
| <input checked="" type="checkbox"/> Objects: High Detail | <input type="checkbox"/> More Shadows | <input checked="" type="checkbox"/> Far Terrain |
| <input checked="" type="checkbox"/> Headlights: Medium Detail | Anisotropic Filtering: <input type="text" value="16x"/> | <input checked="" type="checkbox"/> Trilinear Filtering |
| <input type="text" value="12"/> Max Cars: | Antialiasing: <input type="text" value="4x"/> | <input checked="" type="checkbox"/> Improve car textures |
| <input type="radio"/> No Limit Frame Rate: | <input checked="" type="checkbox"/> Vertex Shaders | <input type="radio"/> Cache/swap nearest cars |

If you are seeing a solid gray bar in the "P" meter, this means your system is incurring a lot of interrupts (or soft page faults) to manage virtual memory. You may benefit from reducing your GPU memory slider and restarting the sim. If this doesn't help try reducing your system working set memory slider. Soft page faults like these may not be that bad, but if you can get rid of them, it will surely help performance.
